

INSTRUCTION MANUAL

Premade Mix & G Competent E. coli Cells

Highlights

- Feature fast transformation kinetics: No heat shock, no lengthy incubations, no outgrowth procedures, no wait!
- High transformation efficiencies: 108-109 transformants/µg plasmid DNA.
- Simple: Mix DNA with cells for a few seconds and plate. Mix & G

Contents

Product Contents and Description	1
Protocol	2, 3
Appendix	3
Ordering Information	4
List of Related Products	5

For Research Use Only Ver. 1.0.9

ZYMO RESEARCH CORP.

Satisfaction of all Zymo Research products is guaranteed. If you should be dissatisfied with this product please call 1-888-882-9682.


Product Contents

	Format			Storage Temp.
Mix & Go Competent E. coli Cells	10 x 100 μl Single- Tube Aliquots	96 x 50 µl Aliquots (12 x 8-Tube Strips)	96 x 50 µl Aliquots (96-well PCR plates)	< -70°C
Instruction Manual	1	1	1	-

Note – Chemically Mix & G competent cells are stable for 6 months at < -70°C. Reagents are routinely tested on a lot-to-lot basis to ensure they provide maximal performance and reliability.

Product Description

Mix & G E. coli are premade chemically competent cells used for simple and highly efficient DNA transformation. Mix & G E. coli cells are made chemically competent by a unique method that completely eliminates the need for heat shock and related procedures. For transformation, DNA can be added directly to Mix & G cells and the mixture spread directly to a culture plate. Transformation efficiencies typically range from 10^8 - 10^9 transformants/µg of pUC19 DNA (see figures below), which make the cells optimal for cloning, sub-cloning, library construction, etc. Premade Mix & G cells are supplied as a pack of 10 convenient 100 µl/tube aliquots or in a 96-well format (12x8-tube strips) of 50 µl/tube.



Mix & Go E. coli cells prepared with ZymoBroth™ display fast transformation kinetics and high transformation efficiencies. Figures above show the transformation kinetics for JM109 and BL21 strains of E. coli generated using ZymoBroth™ and SOB growth media. Plasmid DNA (pUC19) was used for transformation and the data are the averages of three individual experiments.

Note -TM Trademarks of Zymo Research Corporation. This product is for research use only and should only be used by trained professionals. Not intended for use in diagnostic procedures. Wear protective gloves and eye protection. Follow the safety quidelines and rules enacted by your research institution or facility.

Protocol

Pre-warm culture plates to 37°C before starting. Since chemically competent cells are extremely sensitive to changes in temperature, transformation should be performed immediately after thawing.

Transformation Procedure


Single Tube Aliquots

- To a tube of Mix & Go cells thawed on ice, add 1-5 μl plasmid DNA¹, and then mix² gently for a few seconds. (For Mix & Go Transformation, go to Step 3 directly.)
- 2. Immediately place on ice and incubate for 2-5 minutes (maximum 60 minutes).
- 3. Spread 50-100 µl onto a pre-warmed culture plate (Ampicillin selection only, see note below). Incubate the plate at the appropriate temperature (e.g., 37°C) for the colonies to grow.

96-Well Format (8-Tube Strips or PCR Plates)

- 1. To each tube (or well) of Mix & Go cells thawed on ice, add 1-3 μl plasmid DNA¹, and then mix² gently for a few seconds. (For Mix & Go Transformation, go to Step 3 directly.)
- 2. Immediately place on ice and incubate for 2-5 minutes (maximum 60 minutes).
- 3. Spread 25-50 µl of the mixtures onto pre-warmed culture plates (Ampicillin selection only, see note below). Incubate the plate at the appropriate temperature (e.g., 37°C) for the colonies to grow.

Note: The procedures above are for plasmids containing Ampicillin resistant markers. If Kanamycin, Tetracycline, Chloramphenicol, Erythromycin or any non-lactamase selection markers are used, an outgrowth step is required prior to plating. (see Page 3, Notes Section 2 and 4 regarding **Incubation Time & Outgrowth**).



For Technical Assistance, please contact Zymo Research's Technical Department at 1-888-882-9682 or E-mail to tech@zymoresearch.com.

Notes:

¹Keep the added volume of DNA less than 5% of the total.

²To mix cells after DNA addition gently tap the tube with your fingers and then shake the tube downwards in a single motion from the elbow to collect the mixture at the bottom of the tube. Avoid exposing the cells to room temperature for more than a few seconds at a time.

Notes for High Efficiency Transformation

1. E. coli Strains

Different *E. coli* strains vary in their ability to be transformed with DNA. Strains like Zymo 5α, JM109, C600, and TG1 typically yield the highest transformation efficiencies.

2. Incubation Time

The " $\mathit{Min}\ \&\ \mathit{G}$ " procedure (page 2) will work for most transformations using Ampicillin selection and not requiring outgrowth (see Section 4 below). The highest transformation efficiencies can be obtained by incubating $\mathit{Min}\ \&\ \mathit{Go}$ cells with DNA on ice for 2-5 minutes (60 minutes maximum) prior to plating.

3. Prewarming Culture Plates

Chilled plates will decrease Min & G cell transformation efficiency. It is recommended that culture plates be pre-warmed to >20°C (preferably 37°C) prior to plating.

4. Addition of SOC Medium to Transformation Mixtures (Outgrowth)

When selecting with Kanamycin, Tetracycline, etc., an outgrowth performed in SOC medium is required for efficient transformation. In most cases, this step can be omitted when selecting with Ampicillin. After the transformation mixture has incubated on ice for 5-10 min, add 4 volumes of SOC (400 μ l of SOC to 100 μ l of transformation mixture) and incubate for 1 hour at 37°C with gentle shaking at 200-300 rpm. Afterwards, spread the mixture directly onto pre-warmed culture plates. Reducing agents [e.g., DTT (Dithiothreitol) and 2-ME (β -mercaptoethanol)] are not required in this procedure.

Appendix

SOB Recipe: (1 Liter)

Mix the following ingredients:

20 g Bacto-Tryptone 0.58 g NaCl (or 2 ml of 5M NaCl) 10 ml 1M MgCl₂ 5 g Yeast extract 0.19 g KCl (or 0.5 ml 1M KCl) 10 ml 1M MgSO₄

Add ddH₂O to a total volume of 1 liter.

Adjust pH to 6.0-7.0 with NaOH. Autoclave at 10 psi for 15-20 minutes.

SOC Recipe: (100 ml)

Add 1 ml of a 2 M filter-sterilized glucose solution or 2 ml of 20% (w/v) glucose solution to 100 ml of SOB medium.

LB Agar (1 Liter)

10 g of NaCl 10 g of Tryptone 15 g of Agar 5 g of Yeast Extract

Adjust the pH to 7.0 with 5 N NaOH. Autoclave at 15 psi for 15-20 minutes.

Genotypes

JM109

F`traD36 lacl^q Δ (lacZ)M15 pro A+ B+ / e14⁻ (McrA⁻) Δ (lac-proAB)thi gyrA96 (Nal^r)endA1 hsdR17(r_k - r_k - r_k -)relA1 supE44 recA1 (1)

Comments: Partly restriction-deficient; good strain for cloning repetitive DNA(recA $^-$). Suppresses many amber mutations when glutamine is available but not the S_{100} or S_7 mutation of λ , e.g., λ gt11. Can be used for M13 cloning/sequencing and blue/white screening.

XJa

recA1 supE44 endA1 hsdR17 (r_k , m_k) gyrA96 relA1 thi mcrA Δ (lac-proAB) Δ araB:: Δ R, cat F'[traD36 proAB+ lacl lacZ Δ M15]

Comments: Includes chromosomally encoded bacteriophage lambda R gene. Partly restriction-deficient; good strain for cloning repetitive DNA(recA $^-$). Suppresses many amber mutations when glutamine is acceptable but not the S $_{100}$ or S $_7$ mutation of λ , e.g., λ gt11. Can be used for M13 cloning/sequencing and blue/white screening.

XJa(DE3)

recA1 supE44 endA1 hsdR17 (r_k, m_k^+) gyrA96 relA1 thi mcrA Δ(lac-proAB) ΔaraB:: ΔR, cat F'[traD36 proAB+ lacl^q lacZΔM15] ΔDE3

Comments: Includes chromosomally encoded bacteriophage lambda R gene and lambda DE DNA to express T7 RNA Polymerase. Partly restriction-deficient; good strain for cloning repetitive DNA(recA $^{-}$). Suppresses many amber mutations when glutamine is available but not the S_{100} or S_{7} mutation of λ , e.g., λ gt11. Can be used for M13 cloning/sequencing and blue/white screening.

C600

F' [e14-(McrA') or e14* (mcrA*)] thr- 1leuB6 thi- 1 lacY1 supE44 rfbD1 fhuA21; the original C600 is EcoK r*m* McrBC* (2,3)

Zymo 5α (Same as DH5α)

F⁻φ80dlacZΔM15 Δ(lacZYA-argF)U169 deoR, recA1 endA1 hsdR17(r_k⁻m_k⁺phoA supE44 λ⁻ thi-1 gyrA96 relA1 **Comments:** Insert stability due to recA1 mutation. Can be used for blue/white screening, accepts large plasmids due to deoR mutation. High plasmid yield due to endA1 mutation.

Zymo 10B (Same as DH10B)

F- mcrA $\overline{\Delta}$ (mrr-hsdRMS-mcrBC) Φ80lacZ Δ M15 Δ lacX74 recA1 endA1 araD139 Δ (ara leu) 7697 galU galK rpsL nupG λ -Comments: Can be used for blue/white screening and is ideal for cDNA generation and library construction.

<u>HB101</u>

F-Δ(gpt-proA)62 leuB6 supE44 ara-14 galkK2 lacY1 Δ(mcrC-mrr) rpsL20 (Str^r) xyl-5 mtl-1 recA13 (4)

TG1

 $\overline{F'tra}D36 \ lacl^q \ \Delta(lacZ) \ M15 \ proA^+B^+/supE \ \Delta(hsdM-mcrB)5 \ (r_k^-m_k^-McrB^-) \ thi \ \Delta(lac-proAB)$

References:

- 1.) Sheridan, P. et al. Phylogenetic Analysis of Anaerobic Psychrophilic Enrichment Cultures Obtained from a Greenland Glacier Ice Core, Appl. Envir. Microbiol., Apr 2003; 69: 2153 – 2160.
- 2.) Yokobayashi, Y. et al. From the Cover: Directed evolution of a genetic circuit, PNAS, Dec 2002; 99: 16587 16591.
- 3.) Trent, J. et al. A Ubiquitously Expressed Human Hexacoordinate Hemoglobin, J. Biol. Chem., May 2002; 277: 19538 19545.
- 4.) Mourez, M. et al. Mapping dominant-negative mutations of anthrax protective antigen by scanning mutagenesis, PNAS, Nov 2003; 100: 13803 – 13808.

Ordering Information for Premade Mix & Go Competent Cells

Strain	Description	Cat. No.	Size*
JM109	For general cloning, blue-white selection, plasmid isolation. Healthy strain w/ transformation efficiency > 10 ⁸ .	T3003	10 x 100 µl
		T3005	96 x 50 μl (12 x 8-Tube Strips)
	For general cloning, blue-white selection, plasmid isolation. Slow growth w/ certain plasmids not stable. Transformation efficiency > 10 ⁸ .	T3007	10 x 100 μl
		T3009	96 x 50 µl (12 x 8-Tube Strips)
		T3010	96 x 50 µl (PCR Plates)
HB101	For general cloning, plasmid isolation. Transformation efficiency > 10 ⁸ .	T3011	10 x 100 μl
		T3013	96 x 50 µl (12 x 8-Tube Strips)
C600	For general cloning, plasmid isolation. Transformation efficiency > 10 ⁸ .	T3015	10 x 100 μl
TG1	For general cloning, blue-white selection, plasmid isolation. Transformation efficiency > 10 ⁸ .	T3017	10 x 100 μl
	For general cloning, blue-white selection, plasmid isolation. Transformation efficiency > 10 ⁸ . Ideal for cDNA generation and library construction.	T3019	10 x 100 μl
		T3020	96 x 50 µl (12 x 8-Tube Strips)
XJa Autolysis [™]	JM109 w/ chromosomally inserted λ lysozyme gene that is inducible by arabinose.	T3021	10 x 100 μl
XJb (DE3) Autolysis™	BL21(DE3) with chromosomally inserted λ lysozyme gene inducible by arabinose. DE3 lysogen encodes chromosomallyencoded T7 polymerase and is therefore a suitable host for expression of recombinant proteins under the control of the T7 promoter, such as in the pET system.	T3051	10 x 100 μl

Popular E. coli Related Products from Zymo Research

Product	Description	Kit Size	Cat No.
Miz & G E. coli Transformation Kit	Includes all buffers for making up to 20 ml Mix & G chemically competent E. coli. ZymoBroth™ medium is included.	20 ml	T3001
Mia & G E. coli Transformation Buffer Set	Includes all buffers for making up to 60 ml Mix & G chemically competent E. coli. ZymoBroth™ medium is not included.	60 ml	T3002
ZymoBroth™	A specially formulated <i>E. coli</i> growth medium used in the preparation of highly competent <i>E. coli</i> for DNA transformation purposes. Can increase the transformation efficiency from 5 to 100-fold (depending on the <i>E. coli</i> strain).	100 ml 500 ml	M3015-100 M3015-500
Rattler™ Plating Beads	Sterile 5 mm plating beads are convenient and easy to use. No flaming required. Spread cells evenly over the entire culture plate surface.	1 Bottle 5 Bottles	S1001 S1001-5

^{*}Bulk quantities are available upon request. Please contact: <u>busdev@zymoresearch.com</u> or call 1-888-882-9682 for assistance.